



Example API Reporting with PowerBi v1

Summary	2
Overview	2
Challenges	2
Disclaimer	3
Instructions	3
Prerequisites	3
Configuration	3
Reporting Examples	5
Health check column definitions	7



Summary

Automox is the easiest-to-use, most-recommended, most efficient cloud-native solution for endpoint hardening – anywhere, in an instant. Being a cloud-native platform, Automox makes it possible to manage Windows, macOS, and Linux devices with one solution without purchasing physical hardware or installing a management application.

As companies move to internet-based modern solutions, some of the challenges of legacy solutions are immediately solved, while others remain. The purpose of this document is to present the most common challenges and provide guidance on how to utilize native technologies while working to preserve the intent of a cloud-first, infrastructure-less solution.

You can read more about BI here at the Automox blog.

[Using Automox with Business Intelligence Solutions](#)

Overview

Did you know a Business Intelligence solution combined with the Automox Console API can improve cybersecurity by providing improved stakeholder visibility?

In this example, we leverage PowerBI and Powershell to enable Automox users to get your data and present it in a familiar way that everyone can understand.

Using the current API and some of the many already available API calls found on the Automox community site, we can pull our data into PowerBi and display this into a report model.

You can find more API scripts and tricks in our Automox Developer Portal & API Guide:

[Automox Developer Portal & API Guide](#)

Challenges

- Console Reporting is limited to a few reports
- Limited experience with API
- Requests limits aka Pagination
- Nested JSON within JSON within JSON
- No easy way to get device details for all devices, especially if you have more than 5000 devices



Disclaimer

- This isn't a replacement for Automox reporting but an example of using a business intelligence tool with the Automox API.

Instructions

Prerequisites

- API Key from your organization
- Org ID
- Powershell ISE
- Windows 10 or Server 2016+
- [PowerBi Desktop](#)
- Directory path of C:\temp\
- Powershell API script ([GrabAXAPIData.ps1](#) from Github repository)
- Reports Demo v1 PowerBi template ([Automox_Reports_Example_v1_wAPI.pbix](#) from Github repository)

Configuration

1. Create a new folder on your C: drive called temp.
2. Download and save the PowerShell API script to C:\temp
3. Download and save the Automox_Reports_Example_v1_wAPI.pbix to C:\temp
4. Open the script to edit and enter your API & your ORG ID and save it.


```
1 # Update these variables with your API Key, orgID & save directory/filename
2 # This script expects the C:\temp\ path to already exist and will overwrite an existing file
3 #####
4
5 $apiKey = '<YOUR_KEY_HERE>'
6 $orgID = '<YOUR_ORG_HERE>'
7
8 #####
9
10
```

5. Click the Run script button to execute the script. This will generate the required files for the PowerBi reports. The data file are saved in C:\temp\



This PC > OS (C:) > Temp				
<input type="checkbox"/>	Name	Date modified	Type	Size
	GrabAXAPIData.ps1	4/4/2021 12:03 PM	Windows PowerS...	7 KB
	health.csv	4/4/2021 11:31 AM	Microsoft Excel C...	5 KB
	packages.csv	4/4/2021 11:32 AM	Microsoft Excel C...	64 KB
	PackagesWaiting.json	4/4/2021 11:32 AM	JSON Source File	135 KB
	Policies.json	4/4/2021 11:32 AM	JSON Source File	299 KB
	PolicyStats.json	4/4/2021 11:32 AM	JSON Source File	15 KB
	PrePatch.json	4/4/2021 11:32 AM	JSON Source File	3 KB
	ServerGroups.json	4/4/2021 11:32 AM	JSON Source File	11 KB
	Servers.json	4/4/2021 11:32 AM	JSON Source File	136 KB
	SoftwareInv.csv	4/4/2021 11:32 AM	Microsoft Excel C...	136 KB


- Double click to open Automox_Reports_Example_v1_wAPI.pbix from C:\temp\. The template will open and load the data files from step 5.



- Once the data loads and you see the pre-defined reports, save the file as a PowerBi file with the .pbix extension.
- When you want to refresh your report data, just execute the PowerShell script, then click the refresh button in PowerBi.



One glance, and you can see device agent versions, devices online, devices needing a reboot, devices by an operating system, and many more.




With a few clicks, you can sort a column, filter, and export your data.



Click on a group; it will filter the policies and device visualizations.

Click on a policy; it will filter the groups and devices visualization.

Click on a device; it will filter the groups and policies visualization.





Policies give you a great view of all your policies in the Automox console.

Click on a column to sort, or use a filter to focus on a specific policy.

Policies

Name	Package Name	notes	Policy Type	OS Family	Package Version	Device Count
_Client_Pilot_Standard Patches (Wed 1:30pm)		Patch All except definition updates, feature updates	patch	Windows		3
_Client_PROD_Standard Patches (Fri 1:30pm)			patch	Windows		7
_Patch_Advanced_Microsoft_OS and Office		Exclude : SQL, Optional and Recommended Windows Updates, Definition updates, and Feature updates	patch	Windows		0
_Patch_Clients_Defender Updates_Daily			patch	Windows		0
_Patch_Feature Updates_Manual			patch	Windows		8
_Patch_Servicing Stack Update			patch	Windows		10
_Patch_Test - Manual			patch	Windows		9
7-zip	test		required_software	Windows	1.8	0
7-Zip64	7-Zip		required_software	Windows	19.00	2
Clear Browser cache, cookies, history		https://community.automox.com/t/learn-cache-cookies-and-history-from-the-web-chrome/1384	custom	Windows		2
Config Mgr 2012/2 toolkit	ConfigMgr 2012 Toolkit R2	toolkit	required_software	Windows	5.00.7058.1151	6
CS Sensor Installer - Servers	CS Sensor		required_software	Windows	12.2	5
Disable LLMNR		https://community.automox.com/t/worklet-disable-llmnr-security-risk-windows/7413	custom	Windows		2
Firefox International Support Upgrade			custom	Windows		0
Gather Application and System errors		grabbed from https://community.automox.com/t/worklet-windows-event-viewer-output-application-and-system-errors-to-activity-monitor/17251/	custom	Windows		2
Heros_Patch_All			patch	Windows		3
Install Chrome	Google Chrome		required_software	Windows	68.0.3425.146	2
Kyle - Clear Download			custom	Windows		1
Kyle - Open Google			custom	Windows		1
Microsoft Teams - macOS			required_software	Mac	1.0.0.103671	1
Patch - All Test		Testing if Disabled Policy can be attached and if compliance changes based on active/inactive state of this policy	patch	Windows		14
REBOOT-Primary-Patch-Policy			patch	Windows		8
remove MS bloatware			custom	Windows		2
test	notepad++		required_software	Windows	12	0
Uninstall Python 2.7			custom	Windows		2
Uninstall SQL Server 2005			custom	Windows		0

Policy Stats gives you a great view of your policy compliance in the Automox console.

Click on a column to sort, or use a filter to focus on a specific policy.

Policy Stats

Policy Name	Policy Type	Pending	Compliant	Non-Compliant
_Client_Pilot_Standard Patches (Wed 1:30pm)	patch	0	3	0
_Client_PROD_Standard Patches (Fri 1:30pm)	patch	0	7	0
_Patch_Advanced_Microsoft_OS and Office	patch	0	0	0
_Patch_Clients_Defender Updates_Daily	patch	0	0	0
_Patch_Feature Updates_Manual	patch	0	8	0
_Patch_Servicing Stack Update	patch	0	10	0
_Patch_Test - Manual	patch	0	9	0
7-zip	required_software	0	0	0
7-Zipx64	required_software	0	2	0
Clear Browser cache, cookies, history	custom	0	2	0
Config Mgr 2012/2 toolkit	required_software	4	2	0
CS Sensor Installer - Servers	required_software	0	0	0
Disable LLMNR	custom	0	2	0
Firefox International Support Upgrade	custom	0	0	0
Gather Application and System errors	custom	2	0	0
Heros_Patch_All	patch	2	1	0
Install Chrome	required_software	0	2	0
Kyle - Clear Download	custom	1	0	0
Kyle - Open Google	custom	1	0	0
Microsoft Teams - macOS	required_software	0	1	0
Patch - All Test	patch	0	14	0
REBOOT-Primary-Patch-Policy	patch	0	0	0
remove MS bloatware	custom	0	2	0
test	required_software	0	0	0
Uninstall Python 2.7	custom	0	2	0
Uninstall SQL Server 2005	custom	0	2	0
Uninstall SQL Server Compact 3.5	custom	0	2	0
Uninstall Visual Studio 2008	custom	0	2	0
Worklet - Gather Windows Update Events - Manual Run	custom	0	0	0

Pre-patch displays a list of all the scheduled patches per device along with severity and exposure information allowing you to effectively assess internal impact.

Click on a column to sort or

Pre-Patch Report

Name	Device ID	Group	Patch Name	Patches Severity	Patches Cve	Create Time
Thanos	919873	Group B - Test	Security Intelligence Update for Microsoft Defender Antivirus - KB2267602			3/12/2021 9:57:33 AM
Thanos	904773	Group B - Test	Security Intelligence Update for Microsoft Defender Antivirus - KB2267602			2/1/2021 1:38:52 PM



use a filter to focus on a specific device or patch name.

Report displays packages available to install in your organization

Packages Waiting

OS Name	Display Name	Name	Requires Reboot	Cvts	CVE Score	Create Time
10 Enterprise	2021-01 Update for Windows 10 Version 19H2 for x64-based Systems (KB4502171)	7009036-5d81-47d5-93a0-591c075d80dc	True			3/8/2021 5:03:32 PM
10 Enterprise	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			5/12/2020 10:37:58
10 Enterprise	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			5/14/2020 8:34:29 A
10 Enterprise	Security Intelligence Update for Microsoft Defender Antivirus - KB2287602	882287602	False			4/6/2021 6:09:48 PM
10 Enterprise	Security Intelligence Update for Microsoft Defender Antivirus - KB2287602	882287602	False			4/12/2021 8:12:21 A
10 Enterprise	Update for Removal of Adobe Flash Player for Windows 10 Version 19H2 for x64-based Systems (KB4771586)	aeef4446-20c7-4a6b-b6a6-e35a5c154077	True			2/16/2021 5:50:48 P
10 Enterprise Evaluation	2021-01 Update for Windows 10 Version 20H2 for x64-based Systems (KB4502171)	6242011-9879-40c3-63d7-6b608082136d	True			3/10/2021 2:04:49 P
10 Enterprise Evaluation	2021-01 Cumulative Update for .NET Framework 3.5 and 4.8 for Windows 10, version 20H2 for x64 (KB4502171)	65c39a6d-2186-4a1c-b66a-ae6d719a8775	True			2/24/2021 2:13:48 P
10 Enterprise Evaluation	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			11/12/2020 12:57:59
10 Enterprise Evaluation	Security Intelligence Update for Microsoft Defender Antivirus - KB2287602	882287602	False			4/6/2021 1:07:01 PM
10 Home	2019-02 Update for Windows 10 Version 19H2 for x64-based Systems (KB4502171)	70550a6-471a-4d27-b08f-5d110890a06c	True			6/5/2020 7:58:47 A
10 Home	2020-10 Cumulative Update for .NET Framework 3.5, 4.7.2 and 4.8 for Windows 10 Version 19H2 for x64 (KB4579076)	1a62a7a7-5506-4b77-a684-8d5a55079603	True	CVE-2020-1147	9	10/1/2020 7:07:05
10 Home	2020-10 Security Update for Adobe Flash Player for Windows 10 Version 19H2 for x64-based Systems (KB4502171)	1a62a7a7-5506-4b77-a684-8d5a55079603	True	CVE-2020-1147	9	10/1/2020 7:07:05
10 Home	2020-10 Security Update for Adobe Flash Player for Windows 10 Version 19H2 for x64-based Systems (KB4502171)	1a62a7a7-5506-4b77-a684-8d5a55079603	True	ADV2000012	9	10/1/2020 7:07:05
10 Home	2020-10 Cumulative Update for .NET Framework 3.5, 4.7.2 and 4.8 for Windows 10 Version 19H2 for x64 (KB4502171)	1a62a7a7-5506-4b77-a684-8d5a55079603	True			11/23/2020 8:44:41 A
10 Home	2020-11 Cumulative Update for .NET Framework 3.5, 4.7.2 and 4.8 for Windows 10 Version 19H2 for x64 (KB4502171)	1a62a7a7-5506-4b77-a684-8d5a55079603	True			1/28/2021 3:12:18 P
10 Home	Feature update to Windows 10 Version 19H2	6a381e8-4154-41b3-b06a-fc071f3a0e1e	False			1/28/2021 3:12:18 P
10 Home	Microsoft .NET Framework 4.8 for Windows 10 Version 19H2 for x64 (KB4481325)	1a62a7a7-5506-4b77-a684-8d5a55079603	True			5/5/2020 7:19:44 P
10 Home	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			5/12/2020 1:04:37 P
10 Home	Security Intelligence Update for Microsoft Defender Antivirus - KB2287602	882287602	False			2/2/2021 12:44:27 P
10 Home	Windows Malicious Software Removal Tool x64 - v5.85 (KB4502171)	65b8a477-7f58-4bca-b6af-f3a324339f58	True			1/28/2021 3:12:18 P
10 Pro	2021-01 Update for Windows 10 Version 20H2 for x64-based Systems (KB4502171)	6242011-9879-40c3-63d7-6b608082136d	True			3/8/2021 5:03:32 PM
10 Pro	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			5/12/2020 1:04:37 P
10 Pro	Security Intelligence Update for Microsoft Defender Antivirus - KB2287602	882287602	False			4/6/2021 1:02:05 PM
10 Pro	Security Intelligence Update for Microsoft Defender Antivirus - KB2287602	882287602	False			4/12/2021 8:02:10 A
10 Pro for Workstations	Update for Removal of Adobe Flash Player for Windows 10 Version 20H2 for x64-based Systems (KB4771586)	aeef4446-20c7-4a6b-b6a6-e35a5c154077	True			2/16/2021 5:50:48 P
10 Pro for Workstations	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			10/23/2020 15:03:23
10 Pro for Workstations	Microsoft SmartGuard (KB4481325)	ca38a521-af6e-4e26-a5c3-2a96a7108b3e	False			4/15/2021 12:55:43 P

Software Inventory report displays all software installed on all your devices

Software Inventory

Computer	Display Name	Version
DESKTOP-3L433UB	2017-07 Update for Windows 10 Version 1703 for x64-based Systems (KB4013046)	201
DESKTOP-3L433UB	FeatureOnDemandConnectivitySupport - Windows 10 Version 1703 for x64-based Systems - (KB4016006)	201
DESKTOP-3L433UB	FeatureOnDemandInternetExplorer - Windows 10 Version 1703 for x64-based Systems - (KB4016006)	201
DESKTOP-3L433UB	FeatureOnDemandInternetExplorer - Windows 10 Version 1703 for x64-based Systems - (KB4016006)	201
DESKTOP-3L433UB	Google Chrome	78.0.3904.108
DESKTOP-3L433UB	Google Update Helper	1.3.35.141
DESKTOP-3L433UB	LanguageFeatureOnDemand - Windows 10 Version 1703 for x64-based Systems - (KB4016006) [en-US]	201
DESKTOP-3L433UB	MSRSL2019-02 Security Update (KB4502171)	188
DESKTOP-3L433UB	Security Update (KB4502171)	1
DESKTOP-3L433UB	Security Update for Adobe Flash Player	1
DESKTOP-3L433UB	Update (KB4502171)	1
DESKTOP-40TDA5M	2020-10 Cumulative Update for .NET Framework 3.5 and 4.8 for Windows 10 Version 19H2 for x64-based Systems (KB4579076)	200
DESKTOP-40TDA5M	2020-10 Security Update for Adobe Flash Player for Windows 10 Version 19H2 for x64-based Systems (KB4502171)	200
DESKTOP-40TDA5M	2020-10 Update for Windows 10 Version 19H2 for x64-based Systems (KB4502171)	1
DESKTOP-40TDA5M	2021-01 Cumulative Update for Windows 10 Version 20H2 for x64-based Systems (KB4502171)	1
DESKTOP-40TDA5M	2021-01 Cumulative Update for .NET Framework 3.5 and 4.8 for Windows 10 Version 19H2 for x64 (KB4502171)	201
DESKTOP-40TDA5M	Click-to-Run Update Support	201
DESKTOP-40TDA5M	Feature Update to Windows 10 Version 19H2 on Environment Package (KB4502171)	1
DESKTOP-40TDA5M	Microsoft .NET Framework 4.8 for enterprise - en-us	16.0.16328.0274
DESKTOP-40TDA5M	Microsoft Chrome	2.0.0.0204.0025
DESKTOP-40TDA5M	Microsoft SmartGuard	5.1.50918.0
DESKTOP-40TDA5M	Microsoft SmartGuard (KB4481325)	200
DESKTOP-40TDA5M	Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.20.27508	14.20.27508.1
DESKTOP-40TDA5M	Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.20.27508	14.20.27508.1
DESKTOP-40TDA5M	Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.20.27508	14.20.27508
DESKTOP-40TDA5M	Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.20.27508	14.20.27508
DESKTOP-40TDA5M	Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.20.27508	14.20.27508
DESKTOP-40TDA5M	Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.20.27508	14.20.27508
DESKTOP-40TDA5M	MSXML 6.0 RTM Security Update (KB4502171)	103

Health Check display information about your devices a can help you troubleshoot connectivity/patching issues. See the Health check section below for more detail

Health Check

Name	Agent version	OS Version	Auto Update Option	WSUS Config	WSUS Update Source	WSUS Check	Health Check	Last Disconnect Time	Last
client01-leedsingham-local	1.0-30	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/1/2021 5:18:27 PM	4
client02	1.0-30	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful With Error)	True	False	6/7/2021 7:44:48 AM	4
Desktop01	1.0-30	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/6/2021 5:04:36 PM	4
Device-Mac-local	1.0-30	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/8/2021 11:20:31 AM	4
DESKTOP-D50N4U	1.0-31	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False		4
DESKTOP-NCTPDV	1.0-30	5.1.17763.316	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	2/2/2021 1:00:44 AM	2
DESKTOP-D50N4U	1.0-30	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/6/2021 5:04:36 PM	4
DESKTOP-UD2QEH	1.0-30	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/7/2021 7:45:08 AM	4
Device	1.0-31	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False		4
VM-BRONMANS-Mac-local	1.0-31	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False		4
VM-THOR	1.0-31	5.1.19041.610	OPTIONAL=OFF, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/7/2021 7:44:48 AM	4
VM-EUROKROCOM	1.0-30	4.0.0.0	OPTIONAL=ON, ENABLED=ON	WSUS, SERVER=WSUS, REACHABLE=WSUS, MANAGED=WSUS	DISCONNECTED=TRUE (ERROR=Successful)	True	False	6/7/2021 7:44:48 AM	4

Health check column definitions

Name	Device name
------	-------------



Agent Version	Upgrade all agents to version 1.0-31
PS version	PowerShell version on the device
Auto Update Option	<p>Provides the Automatic Update options last collected from each agent during the last scan before I collected the environment data. The settings can be set in different ways (1. By the OS Patch Management settings in the Automox group the agent belongs to, 2. If the OS Patch Management settings in the group is set to keep settings, it will be set locally, by GPO, or if there is another management system configuring patch processes). Our best practice is to only use one method to manage the patch management settings. As an example, if you want Automox to manage the settings, set the "Windows and macOS Patch Management" setting to "Disable OS Automatic Updates", and Set the "Windows Update Source" to either "Windows Update" or "WSUS" depending on where you want the devices of that group to search.</p> <p>Disable other patch configuration settings (example, if you use SCCM/Jamf, stop setting patch configurations via agent settings. If you set Windows Update settings with GPO, remove those settings or set to unconfigured in GPO. The important point is to use only one source to configure these settings.</p> <p>{"ENABLED": "0", "OPTIONS": "off"} for Windows, and {"ENABLED": "0", "OPTIONS": ""} for macOS are the preferred settings. This means that the device will not automatically patch itself, and the Automox policy will define what patches to download, and the schedule for installation.</p>
WSUS Config	WSUS settings defined on the client. WSUS_Server is blank if using Windows Updates as the source, and will list the WSUS server if WSUS is the source. WSUS_Managed, 0 = not WSUS managed, and 1 = WSUS managed. REACHABLE is only relevant if WSUS managed, 0 = Not reachable, 1= Reachable.
WSUS Update Source	Lists if there was an error connecting to the update source, and if it was connected. This will present the devices that failed the update source check visible in the console under compatibility tests.
WMI Check	Windows only, check for WMI corruption
Need Reboot	Device needs a reboot
Last Disconnect time	Lists when a device last disconnected from Automox. if it is empty, it is active. You can use this to identify devices that have not checked recently.
Last Refresh Time	<p>Lists the last time a scan was performed. If the date is missing or is very old, the device has either been offline for a substantial period, or the agent is no longer working correctly.</p> <p>Note: if the agent is v 1.0-25 and the device is active, please contact support as there is a script that can help correct the issue and update the agent to the current version.</p>
Pending Patches	Number of patches needed based on policy at last successful scan.



	Can be compared to Column (patches) for analysis if what is available vs targeted to install.
OS Version	Review for Automox supported OS versions - Automox Agent Requirements
Free (GB)	Free disk space